opentext

Service Desk 24.4 Service Desk Appliance Deployment and Administration Reference

October 2024

Legal Notice

For information about legal notices, trademarks, disclaimers, warranties, export and other use restrictions, U.S. Government rights, patent policy, and FIPS compliance, see https://www.microfocus.com/en-us/legal.

© Copyright 2008 - 2024 Open Text

The only warranties for products and services of Micro Focus and its affiliates and licensors ("Open Text") are set forth in the express warranty statements accompanying such products and services. Nothing herein should be construed as constituting an additional warranty. Micro Focus shall not be liable for technical or editorial errors or omissions contained herein. The information contained herein is subject to change without notice.

About This Guide

This *Service Desk Appliance Deployment and Administration Reference* helps you to deploy and configure Service Desk Appliance to the Service Desk supported virtual infrastructure.

The information in this guide is organized as follows:

- Chapter 1, "Overview," on page 7
- Chapter 2, "System Requirements," on page 9
- Chapter 3, "Appliance Deployment," on page 11
- Chapter 4, "Migrating the Appliance," on page 13
- Chapter 5, "Appliance Management," on page 15
- Chapter 6, "System Management," on page 27
- Chapter 7, "Disaster Preparedness and Recovery," on page 33

Audience

This guide is intended for Service Desk administrators.

Feedback

We want to hear your comments and suggestions about this manual and the other documentation included with this product. Please use the User Comments feature at the bottom of each page of the online documentation.

Additional Documentation

Service Desk is supported by other documentation (in both PDF and HTML formats) that you can use to learn about and implement the product. For additional documentation, see the Service Desk Documentation site.

Contents

	About This Guide 3			
1	Over	view	7	
2	Syste	em Requirements		
	2.1	System Integration	10	
3	Appl	iance Deployment	11	
4	rating the Appliance	13		
	4.1	Migrating to ZENworks Service Desk 24.4 4.1.1 Migrating to ZENworks Service Desk 24.4 Appliance		
5	Appl	iance Management	15	
	5.1 5.2 5.3 5.4 5.5 5.6 5.7 5.8 5.9 5.10 5.11 5.12	Ganglia Configuration5.1.1Enabling Ganglia MonitoringGanglia MonitoringNetworkTimeDigital Certificates5.5.1Using the Digital Certificate Tool5.5.2Using an Existing Certificate and Key Pair5.5.3Activating the Certificate5.5.4Managing Certificates5.5.5Renewing Certificates5.5.6Service Desk Ciphers5.7.1Starting, Stopping, or Restarting System Services5.7.2Setting System Services to Automatic or ManualFirewallAdministrative PasswordsOnline UpdateShutting Down and Restarting Service Desk ApplianceRestarting ZENworks Service Desk Service	16 17 17 18 18 19 20 20 21 22 22 23 23 23 23 23 24 25	
6	Syste	em Management	27	
	6.1 6.2 6.3	Configuration Terminal and File Explorer. 6.2.1 Terminal. 6.2.2 File Explorer Logs.	27 28 28 28	

	6.4	Configuring Service Desk	31
7	Disa	ster Preparedness and Recovery	33
	7.1	Disaster Preparedness	33
		7.1.1 External Database	33
		7.1.2 Embedded Database	34
	7.2	Disaster Recovery	34

1 Overview

Service Desk is available as a virtual Appliance that can be deployed to a supported virtual infrastructure. Service Desk Appliance is built on a customized SUSE Linux Enterprise Server (SLES), and comes pre-installed with Service Desk and thus helps save on operating system license costs.

After deployment, Service Desk can be configured by using an easy to use web based Console. Also, the same console can be used to maintain Service Desk Appliance and perform basic tasks such as executing commands, starting and stopping services, viewing logs, uploading, and downloading files.

You can also tweak basic server settings and monitor the server performance. With the new Service Desk Appliance, it is significantly easier to move to a new major version of Service Desk.

Appliance supports root and sdadmin users who have access to the following privileges:

- Appliance Configuration
 - Ganglia Configuration
 - Ganglia Monitoring
 - Network (root only)
 - Time (root only)
 - Digital Certificates (root only)
 - Storage (root only)
 - System Services
 - Firewall (root only)
 - Administrative Passwords
 - Online Update
 - Shutting Down and Restarting Service Desk Appliance
- Service Desk Appliance
 - Terminal and File Explorer
 - Logs
 - Service Desk Configuration
 - Technician Portal
 - Customer Portal
 - Online Update
 - Shutting Down and Restarting Service Desk Appliance

2 System Requirements

Service Desk Appliance is a 64-bit (x86_64) virtual machine. The following sections provide the requirements for deploying Service Desk Appliance onto a virtual infrastructure:

Table 2-1 Service Desk Appliance Requirement
--

Item	Requirements
Hypervisor	Service Desk Virtual Appliance can be deployed in the following virtual machine environments:
	 VMware ESXi 6.x
	• SUSE XEN on SLES 12 SP4, SLES 12 SP5, SLES 15, SLES 15 SP1
	 Microsoft Hyper-V Windows 10.0
	Citrix XenCenter 8.0
Virtual Machine Configuration	Service Desk Appliance requires the following minimum configuration that have been preconfigured by default:
	• RAM: 4 GB minimum
	Disk Space: 40 GB minimum
	CPU Cores: 2
	Service Desk requires two hard disks. One hard disk of size 40 GB is pre-configured with the Appliance that uses the SLES 12 SP5 operating system and the other hard disk of minimum size 15 GB should be added for the Service Desk data.
	Depending on your requirement, you can increase the pre- configured disk space after deploying Service Desk Appliance.
IP Address	The server must have a static IP address or a permanently leased DHCP address.
Database	Service Desk Appliance comes with pre-installed PostgreSQL database. However, you can choose the other supported database and that must meet the database requirements.
	For more information, see Database Support in the ZENworks Service Desk Platform Support Matrix
Administration Browser	The following are supported web browsers for the Appliance console:
	Latest versions of Google Chrome
	 Latest versions of Mozilla Firefox
	 Latest versions of Microsoft EDGE

Item	Requirements
Supported Languages	These are the supported languages for the Appliance console:
	 English - en
	 French - fr
	 German - de
	 Italian - it
	 Polish - pl
	 Spanish - es

2.1 System Integration

ZENworks Service Desk supports integration with the supported releases of ZENworks Configuration Management.

Appliance Deployment

Fresh deployment of ZENworks Service Desk 24.4 is not supported. However, you can deploy ZENworks Service Desk 24.1, and then update to ZENworks Service Desk 24.4. ZENworks Service Desk 24.4 is available only through Online channel (Online Update channel).

• Fresh Appliance Deployment

To deploy ZENworks Service Desk 24.1, see the Appliance Deployment section in the Service Desk Appliance Deployment and Administration Reference.

• Update to ZENworks Service Desk 24.4

To update to ZENworks Service Desk 24.4, see Migrating the Appliance.

• Updating ZENworks Service Desk older than ZENworks 24.1

If you are using any version older than ZENworks Service Desk 24.1, then refer to ZENworks Service Desk 24.1 Appliance Deployment and Administration Reference.



This chapter contains information about migrating your ZENworks Service Desk Appliance to version 24.4.

ZENworks Service Desk can be migrated to version 24.4 from version 24.3, 24.2 or version 24.1. Refer to the following section to migrate to ZENworks Service Desk 24.4:

• Section 4.1, "Migrating to ZENworks Service Desk 24.4," on page 13

4.1 Migrating to ZENworks Service Desk 24.4

IMPORTANT: For logs, see Section 6.3, "Logs," on page 30

4.1.1 Migrating to ZENworks Service Desk 24.4 Appliance

To migrate to ZENworks Service Desk 24.4 Appliance, refer to the following sections:

- "Pre Migrate" on page 13
- "Migration" on page 13
- "Post Migrate" on page 14

NOTE: ZENworks Service Desk 24.4 will be available only through the Online channel.

Pre Migrate

- Take a snapshot of ZENworks Service Desk Appliance.
- If you are using an external database, then take a backup of the database.
- If any configuration is changed in /etc/init.d/servicedesk.server file, then ensure that you note the changes.
- If any configuration is changed in the Tomcat server such as the web.xml and server.xml files, then ensure that you note the changes.

Migration

- It is recommended to stop the ZENworks Service Desk service before initiating the migration.
 For more information, see Restarting ZENworks Service Desk Service.
- 2 On the ZENworks Service Desk Appliance home page, in the Appliance Configuration section, click **Online Update**.
- 3 In the Online Update page, select Needed Patches from the drop-down, and then click Update Now.

- 4 In the Update Now dialog, read the displayed instructions, and then click OK.
- **5** After completing the migration process, reboot the Appliance.

For more information on rebooting the Appliance, see Shutting Down and Restarting Service Desk Appliance

NOTE: While updating the ZENworks Service Desk, the following error message might be displayed when the appliance takes a longer time to update. Ignore the displayed error message as the update will be completed successfully:

An error occurred while communicating with the server.

Post Migrate

After you migrate to ZENworks Service Desk 24.4, ensure that you perform the following:

- The backup of important configuration file will be available in /vastorage/ backupforzsdv244 location.
- If you have made any changes in the Tomcat server such as the web.xml and server.xml files, then update the changes, if the changes are not available in the file.
- If any memory configuration is modified in the /etc/init.d/servicedesk.server file update the same changes, if the changes are not available in the file.
- In the browser, open the **Technician** portal. The schema upgrade will be initiated automatically, and the upgrade process might be in progress or completed.

A confirmation message is displayed after the upgrade is completed.

If the upgrade fails, then follow the on-screen instructions.

 If you have customized the CSS, and if the existing customization does not work, then you should customize it again. The backup of CSS is available in the /vastorage/LiveTime/ Style location.

Review and replicate the same customization changes in the following UI locations:

```
Setup > Customize > User Portal > CSS
```

```
Setup > Customize > Customer Portal > CSS
```

NOTE:

- 1. In case of any UI related issues, press Ctrl+F5 to refresh the browser cache.
- 2. If any error is displayed, then you can clear the browser cache and try again. If the error persists, contact Customer Support.

5

Appliance Management

In Service Desk Appliance, a web based interface is provided to manage the Appliance. The user interface helps you to configure and perform operations on a Service Desk Server. Based on the logged-in user the tiles are displayed.

To manage Service Desk, see Chapter 6, "System Management," on page 27.

Service Desk Appliance enables you to reconfigure settings of the Appliance, such as administrative passwords, network settings, and certificate settings.

Service Desk Appliance supports root and sdadmin. You can use these users to perform any operations on ZENworks Service Desk Appliance. However, some operations can be performed only using the root user.

To manage Appliance:

1 On a supported web browser, launch the URL to access the Management Console.

The URL (https://<FQDN>:9443 or https://<ipaddress>:9443) that is displayed on the Appliance console.

2 Specify the login with root credentials, then click Log in.

The following options are displayed in the Appliance Configuration:

- Section 5.1, "Ganglia Configuration," on page 15
- Section 5.2, "Ganglia Monitoring," on page 17
- Section 5.3, "Network," on page 17
- Section 5.4, "Time," on page 17
- Section 5.5, "Digital Certificates," on page 18
- Section 5.6, "Storage," on page 22
- Section 5.7, "System Services," on page 22
- Section 5.8, "Firewall," on page 23
- Section 5.9, "Administrative Passwords," on page 23
- Section 5.10, "Online Update," on page 24
- Section 5.11, "Shutting Down and Restarting Service Desk Appliance," on page 25
- Section 5.12, "Restarting ZENworks Service Desk Service," on page 25

5.1 Ganglia Configuration

Ganglia is a scalable, distributed monitoring system that enables you to gather information about the Service Desk Appliance system. The default metrics that you can monitor are CPU, disk, load, memory, network, and process.

NOTE: By default, Ganglia Configuration and Ganglia monitor services will be stopped. If required, you can manually start the Ganglia Configuration and Ganglia monitor services. For more information on enabling Ganglia Monitoring, see "*Enabling Gangila Monitoring*".

- 1 On the Service Desk Appliance home page, in the Appliance Configuration section, click Ganglia Configuration.
- 2 You can change the following configuration options:
 - Enable Full Monitoring Services: Select this option to receive and store metrics from other Appliances, and to allow the Ganglia Web Interface to run on the same device as the Service Desk Appliance.

You can disable Ganglia monitoring by clearing this option. You can perform this only if you have a monitoring system that you want to use for Service Desk Appliance, or if you want to configure a dedicated Appliance for viewing monitoring information. (You can do this by selecting **Unicast** below; then specify the DNS name or IP address of the Appliance where monitoring information is stored.)

- Enable monitoring on this Appliance: Select this option to enable Ganglia monitoring on this Appliance.
 - **Multicast:** Select this option to send monitoring information to other Appliances on the network.
 - Unicast: Select this option to send monitoring information to a single destination.
 - **Publish to:** Specify the server where Ganglia sends monitoring information while it is running in Unicast mode.
- Monitoring Tool Options: Select this option to enable the monitoring tool to access this server through http port 9080 using a similar to http://:9080/gweb/.
- 3 (Optional) Click Reset Database to remove all existing Ganglia metrics from this Appliance.

This option is not applicable to the Service Desk database.

4 Click OK.

For more information about how to use Ganglia monitoring with Service Desk Appliance, see *Section 5.2, "Ganglia Monitoring," on page 17.*

5.1.1 Enabling Ganglia Monitoring

Enable Ganglia monitoring by starting the following services:

- novell-gmond.service
- novell-gmetad.service
- apache2.service

To start the service momentarily, run the systemctl start <service_name> command.

NOTE: Whenever you restart the Appliance, you should run the command to start the monitoring service.

To enable the services permanently run the systemctl enable <service_name> command.

5.2 Ganglia Monitoring

Ganglia is a scalable, distributed monitoring system that enables you to gather information about the Service Desk Appliance system. The default metrics that you can monitor are CPU, disk, load, memory, network, and process. For more information, see *Ganglia*.

5.3 Network

- 1 On the Service Desk Appliance home page, in the Appliance Configuration section, click Network.
- 2 Below DNS Configuration, you can modify the name servers, search domains, and gateway settings for the Service Desk Appliance network.
- **3** Below NIC Configuration, click the ID to modify the IP address, hostname, and network mask of any Network Interface Controller (NIC) associated with the Appliance. (If multiple NICs are configured for Service Desk Appliance, you can configure the additional NICs.)
- 4 Click OK, then restart the Appliance to reflect the changes.
- 5 (Optional) In the Appliance Administration UI (port 9443) Access Restrictions, specify the IP address of any networks for which you want to allow access to the Service Desk Appliance. Leave this blank to allow any network to access the Service Desk Appliance.
- 6 Click OK.

5.4 Time

- 1 On the Service Desk Appliance home page, in the Appliance Configuration section, click Time.
- 2 Change the required time configuration options:
 - NTP Server: Specify the NTP server that you want to use for time synchronization. Multiple servers can be specified by providing spaces.
 - Region: Select the region where Service Desk Appliance is located.
 - **Time Zone:** Select the time zone on which Service Desk Appliance is located.
 - + Hardware Clock Set to UTC
- 3 Click OK.

5.5 Digital Certificates

The Service Desk Appliance ships with a self-signed digital certificate. Instead of using this self-signed certificate, you must use a trusted server certificate that is signed by a trusted Certificate Authority (CA) such as VeriSign or Equifax, which is a paid service, or, if your organization permits, you can use free CA such as AD, eDir, openIdap. Also, update your certificate when you update the Service Desk Appliance software.

Perform the following sections to change the digital certificate for your Service Desk Appliance. You can use the digital certificate tool to create your own certificate and then have it signed by a CA, or you can use an existing certificate and key pair.

- Section 5.5.1, "Using the Digital Certificate Tool," on page 18
- Section 5.5.2, "Using an Existing Certificate and Key Pair," on page 19
- Section 5.5.3, "Activating the Certificate," on page 19
- Section 5.5.4, "Managing Certificates," on page 20
- Section 5.5.5, "Renewing Certificates," on page 20
- Section 5.5.6, "Service Desk Ciphers," on page 21

5.5.1 Using the Digital Certificate Tool

You can perform the following using this page:

- "Creating a Self-Signed Certificate" on page 18
- "Officially Signing Your Certificate" on page 19

Creating a Self-Signed Certificate

- 1 On the Service Desk Appliance home page, under Appliance Management, click Digital Certificates.
- 2 In the Key Store drop-down list, ensure that Web Application Certificates is selected.
- 3 Click File > New Certificate (Key Pair).
- 4 In the Key Certificate (Key Pair) page, specify the following information:
 - Alias: A name that you want to use to identify and manage certificate.
 - Validity (days): How long you want the certificate to be valid.
 - Key Algorithm: Select RSA or DSA.
 - **Key Size:** The required key size.
 - Signature Algorithm: The required signature algorithm.
 - **Common Name (CN):** This must match with the server name in the URL in order for browsers to accept the certificate for SSL communication.
 - Organizational Unit (OU): (Optional) Organizational unit name, such as a department or division.
 - Organization (O): (Optional) Organization name.
 - City or Locality (L): (Optional) City name.

- State or Province (ST): (Optional) State or province name.
- **Two-letter Country Code (C):** (Optional) Two-letter country code. For example, US
- **5** Click **OK** to create the certificate.

After creating the self-signed certificate, you can use the certificate in Service Desk.

However, you can get the certificate signed by a trusted CA. The signing of the certificate is an optional step but recommended. For information, see *"Officially Signing Your Certificate" on page 19*.

Officially Signing Your Certificate

- 1 On the Digital Certificates page, select the certificate that is created, then click File > Certificate Requests > Generate CSR.
- 2 Share your digital certificate with a certificate authority (CA), such as VeriSign.

The CA accepts your Certificate Signing Request (CSR) and generates an official certificate based on the CSR information. The CA then shares the new certificate and certificate chain.

- **3** After receiving the official certificate and certificate chain:
 - 3a Go to the Appliance Configuration page and click Digital Certificates.
 - 3b Click File > Import > Trusted Certificate. Browse for the trusted certificate chain (trusted certificate chain, including intermediate certificate that is received from CA or subordinate CA) that you received from the CA, then click OK.
 - **3c** Select the self-signed certificate, then click File > Certification Request > Import CA Reply.
 - **3d** Browse for and upload the official certificate (Server Certificate) to be used to update the certificate information.
 - **3e** On the Digital Certificates page, the name in the **Issuer** column for your certificate changes to the name of the CA that stamped your certificate.
- **4** Activate the certificate, for information, see "Activating the Certificate" on page 19.

5.5.2 Using an Existing Certificate and Key Pair

When you are using an existing certificate and key pair, use a .P12 or .pfx key pair format.

- 1 On the Digital Certificates page, in the Key Store drop-down, select Web Application Certificate.
- 2 Click File > Import > Trusted Certificate. Browse for and select your existing certificate, then click OK.
- 3 Click File > Import > Trusted Certificate. Browse for and select your existing certificate chain for the certificate that you selected in *Step 2*, then click OK.
- 4 Click File > Import > Key Pair, then browse for and select . P12 or .pfx key pair file, specify password if required, then click OK.
- **5** Activate the certificate, for information see *"Activating the Certificate" on page 19*.

5.5.3 Activating the Certificate

- 1 On the Digital Certificates page, in the Key Store drop-down, select Web Application Certificates.
- 2 Select the certificate that you want to activate, click Set as Active, then click Yes.

- **3** Verify that the certificate and the certificate chain were created correctly by selecting the certificate, then clicking **View Info**.
- 4 Restart the service.

5.5.4 Managing Certificates

All certificates that are included with the Oracle Java package that is bundled with the version of SLES that Service Desk Appliance ships with, are installed when you install Service Desk Appliance.

You can use the Digital Certificates tool on the Service Desk Appliance to remove certificates that are not used by your organization.

Also, you can use the Digital Certificates tool on the Service Desk Appliance to maintain the certificate store by removing certificates that are expired and then installing new certificates as required, according to your organization's security policies.

To access the Digital tool:

1 On the Service Desk Appliance home page, under Appliance Management, click Digital Certificates.

In the Key Store drop-down, under Web Application Certificates, all certificates are displayed. Based on requirement, you can delete the unused certificates.

IMPORTANT: The active certificate must not be deleted.

5.5.5 Renewing Certificates

Depending on your current certificate status, ZENworks Service Desk certificate can be renewed by following any of the following scenarios:

Scenario 1: If the certificate is still valid and want to use the same certificate.

- 1. Share the CSR to the Certificate Authority.
- 2. Get the official server certificate and certificate chain based on CSR from CA
- 3. Import the certificate to ZENworks Service Desk by performing the following steps:
 - a. Go to the Appliance Configuration page and click Digital Certificates.
 - b. In the Key Store field, select Web Application Certificates.
 - c. Click File > Import > Trusted Certificate. Browse for the trusted certificate chain that you received from the CA, then click OK.
 - d. Select the self-signed certificate, then click File > Certification Request > Import CA Reply.
 - e. Browse for and upload the official certificate to be used to update the certificate information.

- f. On the Digital Certificates page, the name in the Issuer column for your certificate changes to the name of the CA that stamped your certificate.
- g. Click View Info the view the validity information.
- 4. Activate the certificate, for information, see Activating the Certificate.

Scenario 2: If the certificate has expired, or you want to use a new certificate

- 1. On the Digital Certificates page, select the certificate that is created, then click File > Certificate Requests > Generate CSR.
- 2. Share the CSR to the Certificate Authority.
- 3. Get the official server certificate and certificate chain based on CSR from CA
- 4. Import the certificate to ZENworks Service Desk by performing the following steps:
 - a. Go to the Appliance Configuration page and click Digital Certificates.
 - b. In the Key Store field, select Web Application Certificates.
 - c. Click File > Import > Trusted Certificate. Browse for the trusted certificate chain that you received from the CA, then click OK.
 - d. Select the self-signed certificate, then click File > Certification Request > Import CA Reply.
 - e. Browse for and upload the official certificate to be used to update the certificate information.
 - f. On the Digital Certificates page, the name in the Issuer column for your certificate changes to the name of the CA that stamped your certificate.
 - g. Click View Info the view the validity information.
- 5. Activate the certificate, for information, see Activating the Certificate.

NOTE: As recommended by top CAs, even though we are renewing the certificate, but in-turn we are creating the certificate every time.

5.5.6 Service Desk Ciphers

Following are the ZENworks Service Desk ciphers that available in the server.xml file:

TLS_ECDHE_ECDSA_WITH_AES_128_GCM_SHA256, TLS_ECDHE_RSA_WITH_AES_128_GCM_SHA256, TLS_RSA_WITH_AES_128_GCM_SHA256, TLS_ECDH_ECDSA_WITH_AES_128_GCM_SHA256, TLS_DHE_RSA_WITH_AES_128_GCM_SHA256, TLS_DHE_DSS_WITH_AES_128_GCM_SHA256, SSL_RSA_WITH_RC4_128_MD5, SSL_RSA_WITH_RC4_128_SHA, TLS_DHE_RSA_WITH_AES_256_CBC_SHA, TLS_DHE_RSA_WITH_AES_256_CBC_SHA256, TLS_DHE_RSA_WITH_AES_128_CBC_SHA256, TLS_DHE_DSS_WITH_AES_128_CBC_SHA256, TLS_DHE_DSS_WITH_AES_128_CBC_SHA256, TLS_DHE_DSS_WITH_AES_128_CBC_SHA256, TLS_DHE_DSS_WITH_AES_128_CBC_SHA256, TLS_DHE_DSS_WITH_AES_128_CBC_SHA256, TLS_DHE_DSS_WITH_AES_128_CBC_SHA256, TLS_DHE_DSS_WITH_AES_256_CBC_SHA256,

```
TLS_DHE_DSS_WITH_AES_256_CBC_SHA256,
TLS_ECDHE_ECDSA_WITH_AES_128_CBC_SHA,
TLS_ECDHE_ECDSA_WITH_AES_128_CBC_SHA256,
TLS_ECDHE_ECDSA_WITH_AES_256_CBC_SHA,
TLS_ECDHE_ECDSA_WITH_AES_256_CBC_SHA384,
TLS ECDHE RSA WITH AES 128 CBC SHA,
TLS_ECDHE_RSA_WITH_AES_128_CBC_SHA256,
TLS ECDHE_RSA_WITH_AES_256_CBC_SHA,
TLS_ECDHE_RSA_WITH_AES_256_CBC_SHA384,
TLS_ECDH_ECDSA_WITH_AES_128_CBC_SHA,
TLS_ECDH_ECDSA_WITH_AES_128_CBC_SHA256,
TLS_ECDH_ECDSA_WITH_AES_256_CBC_SHA,
TLS_ECDH_ECDSA_WITH_AES_256_CBC_SHA384,
TLS_ECDH_RSA_WITH_AES_128_CBC_SHA,
TLS_ECDH_RSA_WITH_AES_128_CBC_SHA256,
TLS_ECDH_RSA_WITH_AES_256_CBC_SHA,
TLS_ECDH_RSA_WITH_AES_256_CBC_SHA384,
TLS_RSA_WITH_AES_128_CBC_SHA,
TLS_RSA_WITH_AES_128_CBC_SHA256,
TLS_RSA_WITH_AES_256_CBC_SHA,
TLS_RSA_WITH_AES_256_CBC_SHA256
```

5.6 Storage

If you have created hard disk partitions (/vastorage and /var), Service Desk Appliance provides tools that allow you to expand the storage space for the /vastorage and /var partitions.

- 1 On the Service Desk Appliance home page, in the Appliance Configuration section, click Storage.
- **2** Use the tools provided by your virtualization platform vendor to expand the virtual disks that contain the partitions your are expanding.
- 3 In the Appliance Disks Containing Unallocated Free Space, select the partitions to be expanded.
- **4** Click Expand partitions.

Appliance services are stopped, the selected partitions are expanded to the size of their respective disks, and Appliance services are restarted.

5 Restart the Appliance so that the operating system detect the disks that are expanded.

5.7 System Services

List of services that is running on the Service Desk Appliance. The following system services are available:

- SSH
- Memcached

In the System Services page, you can perform the following actions:

- Section 5.7.1, "Starting, Stopping, or Restarting System Services," on page 23
- Section 5.7.2, "Setting System Services to Automatic or Manual," on page 23

5.7.1 Starting, Stopping, or Restarting System Services

- 1 In the System Services page, select the service that you want to start, stop, or restart.
- 2 Click Action, then click Start, Stop, or Restart.

5.7.2 Setting System Services to Automatic or Manual

- **1** On the System Services page, select the service that you want to make automatic or manual.
- 2 Click Options, then click Set as Automatic, or Set as Manual.

If you choose **Set as Automatic**, the SSH services will start automatically when you start the Appliance.

If you choose Set as Manual, you need to start or stop the SSH services manually after you start the Appliance.

5.8 Firewall

During the configuration a few ports on Appliance are open. You can view the current firewall configuration from the Service Desk Appliance.

1 On the Service Desk Appliance home page, in the Appliance Configuration section, click **Firewall**. Port numbers are displayed with the current status.

If you have a firewall, you must allow the listed port numbers to ensure that you have a seamless experience with Service Desk Appliance. As a best practice, do not change any port numbers from the default ports.

5.9 Administrative Passwords

- 1 On the Service Desk Appliance home page, in the Appliance Configuration section, click Administrative Passwords.
- 2 Specify the new passwords for the root and sdadmin administrators.

If you are changing the root password, you must first specify the current root password.

- **3** (Optional) Select or clear Allow root access to SSH. When this option is selected, the root user is able to SSH to the Appliance. If this option is not selected, only the zsd user can SSH to the Appliance.
- 4 Click OK.

5.10 Online Update

Online Update enables you to update the Appliance.

1 On the Service Desk Appliance home page, in the Appliance Configuration section, click Online Update.

You can perform the following actions:

• **Register:** Enables you to register with Micro Focus Customer Center (MFCC) server or a Local Subscription Management Tool (SMT) server from where you can download software updates and install automatically to update the product.

To register online update service:

- 1. Click the Register tab.
- 2. Choose the type of service Local SMT (Subscription Management Tool) or Novell Customer Center (NCC).

Based on the service type, specify the following:

Local SMT

- Hostname: The hostname of the server from where you want to download.
- SSL Cert URL (optional): The SSL certificate to communicate with the server.
- Namespace path (optional): The name space of the file or directory.

Novell Customer

- Email: The email address to receive the updates on Service Desk suite.
- Activation key: The activation key for the server base license.
- Allow data send: choose how you want to receive the data Hardware Profile or Optional information.
- 3. Click Register.
- Update Now: After registration, click Update Now to trigger downloaded updates.
- Schedule: After registration, you can configure type of updates to download and whether to automatically agree with the licenses.

To schedule online update:

- 1. Click the Schedule tab.
- 2. Select a schedule for download updates (Manual, Daily, Weekly, Monthly).

IMPORTANT: We recommend that you schedule online updates only for updating noninteractive security patches on ZENworks Service Desk Appliance 7.5 or later. Rest of the patches including upgrade to newer version of Service Desk can be done manually as it impacts the system and might cause down-time of server.

- View Info: Displays the list of installed and downloaded software updates.
- **Refresh:** Refreshes the status of updates on the Appliance.

5.11 Shutting Down and Restarting Service Desk Appliance

To shutdown or restart the appliance, on the Service Desk Appliance home page, in the Appliance Configuration section, click **Reboot** or **Shutdown**.

5.12 Restarting ZENworks Service Desk Service

To stop, start or restart ZENworks Service Desk service, perform any one of the following actions:

Using Appliance UI:

On the Service Desk Appliance home page, in the ZENworks Service Desk Appliance section, click Restart Services, select ZENworks Service Desk, and the click Stop.

Using Command Prompt:

```
To stop/start/restart the servicedesk service from the command prompt, run the systemctl start | stop | restart servicedesk command or service servicedesk start | stop | restart.
```

Example:

- To start the servicedesk service, run the systemctl start servicedesk command.
- To start the servicedesk service, run the service servicedesk start command.

System Management

The user interface helps you to configure and perform operations on a Service Desk Server. Based on the logged-in user the tiles are displayed.

On Service Desk, the root or sdadmin user has all privileges. The sdadmin user is used as a Service Desk administrator to perform day-to-day activities in Service Desk.

The following operations can be performed by root and sdadmin:

- Explore all the files and folders of the Appliance system
- View logs
- View and edit the Service Desk configuration settings
- Restart both Appliance and Service Desk
- Launch a terminal and execute commands

To manage Service Desk Appliance:

1 Launch the URL on a supported web browser to access the Management Console.

For example: https://<FQDN>:9443 or https://<ipaddress>:9443

2 Specify the login credentials, then click **Log in**.

If you log in as a root or sdadmin user, the following options are displayed in the Service Desk section:

NOTE: In case of any UI related issues, press Ctrl+F5 to refresh the browser cache.

- Section 6.1, "Configuration," on page 27
- Section 6.2, "Terminal and File Explorer," on page 28
- Section 6.3, "Logs," on page 30
- Section 6.4, "Configuring Service Desk," on page 31

6.1 Configuration

The Service Desk Configuration page is enabled only after Service Desk is successfully configured.

1 On the Service Desk Appliance home page, in the Service Desk Appliance section, click Service Desk Configuration.

The Service Desk Configuration page has the Summary of database configuration.

The Summary enables you to view the Service Desk Server details. This includes information about the Certificate, Service Desk Database, and Appliance details, such as type of hypervisor used, operating system, RAM and file system and HDD details.

The Appliance comes with built-in 40 GB of <code>rootfs</code> file system that is mounted on root directory. The Additional hard disk that is added will be attached to the /dev/sdb1 and mounted on /vastorage. All Service Desk related configurations, log files, certificates, and binaries are stored on the additional hard disk.

2 Click Database Configuration to change the password of embedded database or to connect to an external database. This page also displays the current database configurations.

To change the Embedded Database password:

- 2a Choose the Embedded Database.
- 2b Select Change Password, specify the new password and confirm, and then click OK.

or

2c To use an External Database:

Choose External Database and click OK.

2d Go to the **Appliance Home** page, click **Technician Portal**, and configure the external database.

6.2 Terminal and File Explorer

This tile launches an integrated view for File System Explorer and Terminal.

- Section 6.2.1, "Terminal," on page 28
- Section 6.2.2, "File Explorer," on page 29

6.2.1 Terminal

SSH service needs to be running for terminal to work. SSH service is started by default. If the SSH service is not running, perform the following steps:

- 1 On the Service Desk Appliance home page, in the Appliance Configuration, click the System Services icon.
- 2 Select the SSH service on the System Services page.
- 3 Click Action, then click Start.

Set the SSH service to Automatic, if you want to restart the SSH service automatically after you reboot the device.

4 On the Service Desk Appliance home page, in the Service Desk section, click Terminal & File Explorer.

A new browser window launches two frames that display a **File Explorer** (for performing file operations) and a **Terminal**. Whenever you close the Terminal browser or tab, then a confirmation message is displayed.

If you log in as sdadmin or root user, you can open a terminal session.

You can perform file operations by using an embedded File Explorer that enables you to transfer content between the local and the remote file systems. You can also open new terminals rooted at any folder in the remote file system.

You can launch more than one terminal by clicking **New Terminal**. By default, a maximum of five terminals can be launched.

To configure with any other value than the default value of the terminal:

- 1 Go to /etc/opt/novell/base
- **2** Open the terminal_config.properties file.
- **3** Change the maxTerminalsPerBrowser value with the required value, then save the file.

To select a theme (foreground and background color) for the terminals:

1 Click the Settings 💁 icon, then select the required terminal theme.

To create a theme:

- 1 Go to /etc/opt/novell/base
- 2 Open the terminal-themes.xml file.
- **3** Add your own theme, then save the file. For example:

```
<theme>
        <name>example</name>
        <background-color>#000000</background-color>
        <foreground-color>yellow</foreground-color>
</theme>
```

6.2.2 File Explorer

1 On the Service Desk Appliance home page, in the Service Desk section, click Terminal & File Explorer.

A new browser window launches two frames that display a File Explorer (for performing file operations) and a Terminal (SSH).

This enables you to perform operations on files and folders.

- The file operations are based on user privileges (POSIX file permissions).
- If you log in as sdadmin, all file operations are executed as sdadmin user.
- If you log in as root, all file operations are executed as root user.
- In the tabular view, a context menu is available with these options: Open Terminal, Refresh, Upload, Delete, and Rename.
- The Tree View for Appliance file system displays the Appliance file system as a tree. Only folders are displayed in the tree view. The following options are available Open Terminal, Refresh, Cut, Copy, Paste, Delete, Rename, New Folder, Download, and Upload.
- File explorer enables you to explore the Appliance's (SLES -Unix) file system, breadcrumb navigation, upload, download, refresh, rename, create, delete, or, CCP operations (cut, copy, and paste).

Below the file path, a toolbar is displayed and you can perform the following:

lcon	Name	Description
0	Terminal Settings	To change the terminal theme display settings.
6	Select Path	To select file path that is displayed on the breadcrumb.
0	Settings	To configure show or hide files.
/	Breadcrumb	Displays the path for selected file or folder.
t	Parent Directory	Display the contents of the parent folder in the tabular view.
*	Download	To download files and folders under a specified folder.
1	Upload	Supports multiple file upload; folder upload is not supported.
	New folder	Creates a folder in the current folder.
	New file	Creates a new file in the current folder.
2	Refresh	Updates the tabular view with the latest contents from the Appliance.
۵	Delete	Enables you to delete multiple files and folders under a specified folder.

6.3 Logs

All log files that are monitored on Service Desk Appliance are organized in a virtual tree structure and path of the particular file or folder is displayed. Log files can be viewed in the Tail mode or View From Start mode.

In the Tail mode, a log file is displayed from the end of log file.

All logs for the Appliance, OS and Service Desk are available in the /var/opt/novell/log/ location.

In the View From Start mode, a log file is displayed from the start of the log file. Whenever log files span across multiple version of files, then starting from the first version of that file the content is displayed.

1 On the Service Desk Appliance home page, in the Service Desk section, click Logs.

This enables you to view logs of the Service Desk Server. Logs are categorized based on Appliance logs, operating system logs, and Service Desk logs. With-in Service Desk, logs are categorized based on different components.

Logs has the following options:

• View, View From Start, and Refresh

- Download enables you to download a log file or a folder.
- **Resume** and **Pause** enable you to tail log files to see the latest information. You can configure the refresh interval of a tail by specifying the **Refresh** time in **Seconds**. Refresh specifies the interval of time between two requests. By default **Refresh** is set to one second.

Specify Lines to load to control the number of lines to be retrieved for the tail interval. By default Lines to load is set to 100.

Control the speed in which log file is displayed. Log files are loaded by making multiple HTTP requests in periodic intervals of time. Each request loads a configurable number of lines.

- Clear enables you to clear the current displayed logs. However, logs will not be cleared in Service Desk Appliance. To see the cleared logs, start the log file.
- Search enables you to filter logs based on the search criteria. You can use tail and grep to monitor log files from the terminal. The log viewer provides a GUI for tailing and filtering the content in log files. You can search based on log level such as INFO, ERROR, and DEBUG and also with regular expressions (AND and OR).

6.4 Configuring Service Desk

To configure Service Desk:

- **1** In the Service Desk Appliance home page, in the Service Desk Appliance section, click Technician Portal.
- 2 In the ZENworks Service Desk login page, specify the login credentials that you specified during configuration.

To open the new customer portal, click Customer Portal.

By default super/super and admin/admin will be your login credentials.

NOTE: If an LDAP User source is configured for a Supervisor super/super is disabled.

Disaster Preparedness and Recovery

This section explains how you can protect ZENworks Service Desk data and be prepared if an organizational risk assessment identifies a need for a recovery mechanism. Backing up a database provides a snapshot of the database, where the data is in a consistent state. If you are facing any issues with the product or the database, then the database can be recovered.

- Section 7.1, "Disaster Preparedness," on page 33
- Section 7.2, "Disaster Recovery," on page 34

For best results, ensure that backup copies are made on a consistent, regular basis to minimize the amount of data loss between backups.

7.1 Disaster Preparedness

ZENworks Service Desk can either be used with an embedded or an external database. Based on your database, see the following sections:

- Section 7.1.1, "External Database," on page 33
- Section 7.1.2, "Embedded Database," on page 34

7.1.1 External Database

If you are using an external database, then you have to take a backup of the database and snapshot of the Appliance.

- 1. Database Backup: If you have taken a backup of the database, then following configurations or data are included in the backup:
 - e-Mail (Server, Setup)
 - Licensing (License, Host, Users)
 - LDAP (Server, Advanced connection info: Type, Domains, Security, Host or Port number, Username, UserNode or BaseDN, Groups and GUID)
 - AD or eDir Group Information
 - AMIE (Setup connection info: Server Type, DB Type, Hosts or Port number, Name, Username, Schema, Catalog, etc.)
 - ZENworks (General, OpenID lists connection info: ZCM Server Address)
 - Customized privileges
- 2. Appliance Snapshot: system.properties of the Appliance, then All CSS and Banners customizations are saved. Database (connection info: Type, Host or Port number, Db, Username, password), Java Heap Memory configurations and the system.properties file.

7.1.2 Embedded Database

If you are using an embedded database that is provided with ZENworks Service Desk Appliance, then just by taking a snapshot of the Appliance (or a take backup of the second disk), you can be prepared for the disaster. Following data are saved by taking snapshot of the appliance:

- 1. All CSS and Banners customizations that are stored in the second disk.
- 2. e-Mail (Server, Setup)
- 3. Licensing (License, Host, Users)
- 4. Database connection info: Type, Host or Port number, Db, Username, password)
- 5. LDAP (Server, Advanced connection info: Type, Domains, Security, Host or Port number, Username, UserNode or BaseDN, Groups and GUID)
- 6. AD, AzureAD or eDir Group Information
- 7. AMIE (Setup connection info: Server Type, DB Type, Hosts or Port number, Name, Username, Schema, Catalog, etc.)
- 8. ZENworks (General, OpenID lists connection info: ZCM Server Address)
- 9. Customized privileges

7.2 Disaster Recovery

If you are facing any issues with the product or the database, then the backup data enables you to restore your ZENworks Service Desk to a stable state.

IMPORTANT: The data that was captured in the system after taking the backup will be lost. Hence, it is recommended that backup copies are made on a consistent, regular basis to minimize the amount of data loss between backups.

- If you are using an external database, then ensure that you restore the database backup and roll back the Appliance (or restore second hard disk) to a stable snapshot.
- If you are using an embedded database, then ensure that you roll back the Appliance (or restore second hard disk) to a stable snapshot.