

ZENworks 2017 Update 2 Troubleshooting Full Disk Encryption

February 2018



This document provides troubleshooting guidelines for common problems related to ZENworks Full Disk Encryption. If, after completing the troubleshooting steps, the problem is not resolved, you should contact [Technical Support \(https://www.novell.com/support/\)](https://www.novell.com/support/) for additional help.

1 Windows PE Emergency Recovery Disk (ERD) is not working

- Make sure you have installed the correct WAIK architecture (32-bit vs 64-bit)
- If you manually created the ERD, use the PowerShell script provided in the Cool Solutions “[Windows Powershell script to create a Windows PE emergency recovery disk for ZENworks Full Disk Encryption](#)” article.
- Try creating the ERD using the ADK for Windows 8 instead of Windows AIK. See “[Creating a Windows PE Emergency Recovery Disk](#)” in the *ZENworks Full Disk Encryption Emergency Recovery Reference*.
- Try burning the ERD to a DVD rather than a CD.

2 The ZENworks PBA is not booting to the Windows operating system

Symptoms: After logging in to the PBA, the user encounters a black screen or GRUB error and the device does not boot the operating system.

After pre-boot authentication occurs, the BIOS or UEFI settings must be correctly set for Windows. With older or unusual hardware configurations, the standard ZENworks PBA boot method and Linux kernel configuration used to provide the BIOS settings might not work, resulting in hardware that does not function correctly or is not recognized by Windows.

To resolve this issue, you need to repair the device’s master boot record (MBR) or GUID partitions tables (GPT) so that the device boots directly to the operating system. You need to then modify the Direct Media Interface (DMI) file provided by ZENworks Full Disk Encryption so that it includes the correct settings to boot the device.

1. Repair the device’s MBR or GPT:
 - ♦ **Windows 7:** Boot the device from a Windows 7 installation disk. When the Windows 7 splash screen displays, click **Repair your computer**. After the scan completes, select the Windows installation to repair and continue. If you are prompted to repair the problem automatically, select **No**. When the System Recovery Options dialog is displayed, click the **Command Prompt** option, then enter `bootrec.exe /fixmbr` at the command prompt. You should see a success message after running the command. Type `exit` to exit out of the command prompt and continue to boot into Windows.

If you don't have a Windows 7 installation disk, you can use a Windows 7 system recovery disk. To create the disk on a working Windows 7 machine, click **Start > All Programs > Maintenance > Create a System Repair Disc**.

- ♦ **Windows 8 or Windows 10:** Boot the device from a Windows 8 or Windows 10 installation disk, respectively. When the Windows splash screen displays, click **Repair your computer**. On the next screen, select **Troubleshoot**, then select **Advanced options**. From the Advanced options, launch a command prompt, then enter `bootrec.exe /fixmbr`. When the operation is finished, reboot the device.

If you don't have a Windows 8 or Windows 10 installation disk, you can use a system recovery disk created from the Windows 8 ADK and the ZENworks WinPE plugin.

2. Modify the `dmi.ini` file settings:

The `dmi.ini` file provides the boot method to be used to transition from the Linux kernel to the Windows operating system. The file contains a default boot setting and a list of known hardware configurations that require different boot settings. The default setting is applied unless the device's hardware configuration is in the list. The `dmi.ini` file's default setting and first few entries are shown below:

```
[default]
KICKSTART=FAST


[FUJITSU SIEMENS,LIFEBOOK C1110]
DMI_SYS_VENDOR=FUJITSU SIEMENS
DMI_PRODUCT_NAME=LIFEBOOK C1110
KICKSTART=BIOS

[LENOVO,20021,2959]
DMI_SYS_VENDOR=LENOVO
DMI_PRODUCT_NAME=20021,2959
KICKSTART=BIOS

[LENOVO,0831CTO]
DMI_SYS_VENDOR=LENOVO
DMI_PRODUCT_NAME=0831CTO
KICKSTART=KEXEC
KERNEL_PARAM=pai=snb-enable-ahci-to-legacy
```

You need to discover the correct settings for your device and add an entry to the `dmi.ini` file. This discovery is a trial and error process; you will need to try different settings until one enables the machine to boot successfully.

- a. On the device, open a command prompt with Administrator privileges, change to the `c:\windows\nac\sbs` directory, then run the `dmiconfig dump` command to see the device's current `dmi.ini` settings.



```
Administrator: C:\Windows\System32\cmd.exe
C:\Windows\NAC\SBS>dmiconfig dump
[LENOVO,2767AL9]
DMI_SYS_VENDOR=LENOVO
DMI_PRODUCT_NAME=2767AL9
;KICKSTART=FAST
C:\Windows\NAC\SBS>
```

- b. Create a new dmi.ini text file on your desktop and copy the results from the dmiconfig dump into the file. Edit the last line to remove the semicolon and change the KICKSTART value to another boot option (listed below), as shown in the following example:

```

dmi.ini - Notepad
File Edit Format View Help
[LENOVO,2767AL9]
DMI_SYS_VENDOR=LENOVO
DMI_PRODUCT_NAME=2767AL9
KICKSTART=BIOS

```

Finding the correct setting is a trial and error process. The possible DMI settings are listed below in the order we recommend trying them. For some settings, recommendations are given for when to use them.

Setting	Example
KICKSTART=BIOS This setting is effective in resolving issues where the ZENworks PBA displays the credential or user capture prompt but then fails to boot to Windows.	<pre> [LENOVO,2767AL9] DMI_SYS_VENDOR=LENOVO DMI_PRODUCT_NAME=2767AL9 KICKSTART=BIOS </pre>
KICKSTART=KEXEC	<pre> [LENOVO,2767AL9] DMI_SYS_VENDOR=LENOVO DMI_PRODUCT_NAME=2767AL9 KICKSTART=KEXEC </pre>
KICKSTART=FAST	<pre> [LENOVO,2767AL9] DMI_SYS_VENDOR=LENOVO DMI_PRODUCT_NAME=2767AL9 KICKSTART=FAST </pre>
KICKSTART=KEXEC KERNEL_PARAM=pci=snb-enable-ahci-to-legacy	<pre> [LENOVO,2767AL9] DMI_SYS_VENDOR=LENOVO DMI_PRODUCT_NAME=2767AL9 KICKSTART=KEXEC KERNEL_PARAM=pci=snb-enable-ahci-to-legacy </pre>
KICKSTART=KEXEC KERNEL=/boot/bzImage-acpi This setting is effective in resolving issues where the ZENworks PBA screen displays but the credential or user capture prompt never displays.	<pre> [LENOVO,2767AL9] DMI_SYS_VENDOR=LENOVO DMI_PRODUCT_NAME=2767AL9 KICKSTART=KEXEC KERNEL=/boot/bzImage-acpi </pre>

Setting	Example
KICKSTART=KEXEC	[LENOVO,2767AL9]
KERNEL_PARAM=pci=snb-enable-ahci-to-legacy	DMI_SYS_VENDOR=LENOVO DMI_PRODUCT_NAME=2767AL9 KICKSTART=KEXEC
KERNEL=/boot/bzImage-acpi	KERNEL_PARAM=pci=snb-enable-ahci-to-legacy KERNEL=/boot/bzImage-acpi

- c. In the `c:\windows\nac\sbs` directory, make a backup copy of the current `dmi.ini` file, then copy your edited `dmi.ini` file to the directory.
- d. Open a command prompt with Administrator privileges, change to the `c:\windows\nac\sbs` directory, then run the `dmiconfig import --force` command to import the settings from the new `dmi.ini` file. Run `dmiconfig dump` to verify the change.

```

Administrator: C:\Windows\System32\cmd.exe

C:\Windows\NAC\SBS>dmiconfig import --force

C:\Windows\NAC\SBS>dmiconfig dump
[LENOVO,2767AL9]
DMI_SYS_VENDOR=LENOVO
DMI_PRODUCT_NAME=2767AL9
KICKSTART=BIOS

C:\Windows\NAC\SBS>

```

- e. Reboot the device. If the device fails to boot to the Windows operating system, repair the MBR, then repeat the above process using another setting.
- f. After you find the correct setting, you can edit your Full Disk Encryption policy to add it to the policy's `dmi.ini` file (ZENworks Control Center > **Policies** > Full Disk Encryption policy details > **DMI Settings** tab > **Edit**).

3 The ZENworks Endpoint Security service (ZESService) is crashing

- Check to see if the device is using the Intel IRRT driver. This driver causes the device to crash and is not supported. If the device is using the driver:
 1. Disable the driver through the device's adapter settings.
 2. Reboot the device to BIOS and change from IRRT to AHCI mode.

4 New disk drive not encrypting with existing Full Disk Encryption policy

When you apply a Full Disk Encryption policy to a device, you have the option to encrypt all local fixed volumes or specify the volumes that will be encrypted. Once the policy is applied, the specified volumes are encrypted.

If you add a new disk drive to the device, or you want to specify another volume on the device for encryption, the policy must be removed, including disk decryption, and then be reapplied to recognize the new volumes. If the existing policy is not set to encrypt all local fixed volumes, you need to edit the Local Fixed Volumes setting in the policy to recognize the new volumes before reapplying the policy and encrypting the drives.

For information about removing, editing, and applying Full Disk Encryption policies, see the *ZENworks Full Disk Encryption Policy Reference*.

5 Legal Notice

For information about legal notices, trademarks, disclaimers, warranties, export and other use restrictions, U.S. Government rights, patent policy, and FIPS compliance, see <https://www.novell.com/company/legal/>.

Copyright © 2018 Micro Focus Software Inc. All Rights Reserved.